

Deltek Acumen 6.0

Technical Installation Guide

December 8, 2014

While Deltek has attempted to verify that the information in this document is accurate and complete, some typographical or technical errors may exist. The recipient of this document is solely responsible for all decisions relating to or use of the information provided herein.

The information contained in this publication is effective as of the publication date below and is subject to change without notice.

This publication contains proprietary information that is protected by copyright. All rights are reserved. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, or translated into another language, without the prior written consent of Deltek, Inc.

This edition published December 2014.

© 2014 Deltek, Inc.

Deltek's software is also protected by copyright law and constitutes valuable confidential and proprietary information of Deltek, Inc. and its licensors. The Deltek software, and all related documentation, is provided for use only in accordance with the terms of the license agreement. Unauthorized reproduction or distribution of the program or any portion thereof could result in severe civil or criminal penalties.

All trademarks are the property of their respective owners.

Contents

- Overview 1
- If You Need Assistance 2
 - Customer Services 2
 - Customer Care Connect Site 2
- Pre-Installation Information 4
 - Hardware Requirements 4
 - Compatibility Matrix 4
- Installation and Updates 6
 - Initial Installation 6
 - Updates 6
 - Manually Check for Updates 7
 - Check to See if an Update is Installed 7
- Configuring the Fuse.exe.config File 8
 - Useful Configuration File Settings 8
- Installing Acumen in a Citrix® XenApp™ Environment 10
 - Installing Acumen on the XenApp Servers 10
 - Publish Acumen in XenApp 11
 - Testing the Deployment 21
 - Troubleshooting 22
- Appendix A: Example of a Fuse.exe.config File 23

Overview

This guide contains technical installation and setup information for the staff at your company who maintain the hardware and software required to install Deltek Acumen.

If You Need Assistance

If you need assistance installing, implementing, or using Acumen, Deltek makes a wealth of information and expertise readily available to you.

Customer Services

For over 20 years, Deltek has maintained close relationships with client firms, helping with their problems, listening to their needs, and getting to know their individual business environments. A full range of customer services has grown out of this close contact, including the following:

- Extensive self-support options through the Customer Care Connect Web portal.
- Phone and email support from Customer Care analysts
- Technical services
- Consulting services
- Custom programming
- Classroom, on-site, and Web-based training



[Find out more about these and other services from the Customer Care Connect site.](#)

Customer Care Connect Site

The Deltek Customer Care Connect site is a support Web portal for Deltek customers who purchase an Ongoing Support Plan (OSP).

The following are some of the many options you have at the Customer Care Connect site:

- Download the latest versions of your Deltek products
- Search Deltek's knowledge base
- Ask questions, exchange ideas, and share knowledge with other Deltek customers through the Deltek Connect Customer Forums
- Display or download product information, such as release notes, user guides, technical information, and white papers
- Submit a support case and check on its progress
- Transfer requested files to a Customer Care analyst
- Use Quick Chat to submit a question to a Customer Care analyst online
- Subscribe to Deltek communications about your Deltek products and services
- Receive alerts of new Deltek releases and hot fixes



[If you need assistance using the Customer Care Connect site, the online help available on the site provides answers for most questions](#)

Access Customer Care Connect

To access the Customer Care Connect site, complete the following steps:

1. Go to <http://support.deltek.com>.
2. Enter your Customer Care Connect **Username** and **Password**.
3. Click **Log In**.



If you do not have a username and password for the Customer Care Connect site, contact your firm's Acumen Administrator.

If you forget your username or password, you can click the **Account Assistance** button on the login screen for help.

Pre-Installation Information

Acumen is a Windows application. It requires no backend database installation. The system requirements are listed below.

Hardware Requirements

Server

In server environments, Deltek recommends:

Component	Recommended Hardware
CPU	<ul style="list-style-type: none"> Multi-core CPU — Acumen is a multi-threaded application that takes advantage of multi-core processors.
Acumen*	<ul style="list-style-type: none"> 1GB — Typical project size is <10K records. 2GB — Typical project size is 10K - 100K records. 3GB — Typical project size is >100K records.

* Per concurrent Acumen instance and in addition to any memory needed for the operating system and other applications that may run in parallel with Acumen.

If the operating system is a 64-bit version, then Acumen will take advantage of the extended address space and Deltek therefore recommends adding additional memory to improve performance.

Standalone Computer

- Hard Drive Space — 300MB recommended
- RAM — 4GB RAM recommended

Compatibility Matrix

Embedded Technology	Supported Deployment Technology
<p>Microsoft .NET Framework version 4.0 SP1 (included as part of the Acumen installer)</p>	<p>Acumen is a Windows application. It requires no backend database installation. System requirements are as follows:</p> <p>Operating System</p> <ul style="list-style-type: none"> Microsoft Windows <ul style="list-style-type: none"> Windows Vista SP1 or later Windows Server 2003 Windows Server 2003 R2 Windows Server 2008 Windows Server 2008 R2 Windows Server 2012

Embedded Technology	Supported Deployment Technology
	<ul style="list-style-type: none"> ▪ Windows 7 ▪ Windows 8 ▪ Windows 8.1 ▪ Mac OSX <ul style="list-style-type: none"> ▪ Requires Parallels or VMWare ▪ Citrix (Verified Compatibility) XenApp <ul style="list-style-type: none"> ▪ 6.5 (64-bit) ▪ 6.0 (64-bit) Other <ul style="list-style-type: none"> ▪ DirectX 7.0 (minimum), DirectX 9.0 or higher (recommended)

Project Management Platform Integration

Acumen integrates with multiple project management platforms. Each Acumen workbook can contain projects from any of the following platforms:

- MS Project 2007/2010, MS Project Server 2007 and above
Links to MS Project files in one of the following ways:
 - Through your installed copy of MS Project
 - Directly reading an MS Project file (without needing MS Project installed on your PC)
- Primavera P6 (versions 5.x, 6.x, 7.x and 8.x)
- Primavera P3
- Oracle Pertmaster/Risk Analysis V8.x
- Asta PowerProject
- UN/CEFACT XML (IPMR Format 6 v1.0)
- Deltek Open Plan® V3.x
- Deltek Cobra® (Earned Value)
- Deltek Risk+
- ARES PRISM G2
- Phoenix Project Manager
- Safran Project 5
- RiskBook — You will need a RiskBook license and one of the following browsers:
 - Internet Explorer 9 or higher
 - Google Chrome version 12 or higher
 - Safari 6.0 or higher
 - Firefox 9 or higher

Installation and Updates

Initial Installation

You can install Acumen using online or offline installation.

After installation, the Acumen software shortcuts display within a sub-menu under the Deltek folder in the Start menu.

Acumen includes sample files and documentation. These can be found in the Acumen Fuse folder within your Documents folder on your computer.

Online Installation

Acumen is installed from an online virtual DVD. The Acumen installer uses Microsoft® ClickOnce technology which allows you to install and maintain updates to Acumen without the need for administrative rights to your computer.

To install Acumen, use the following link: <https://dsm.deltek.com/files/fuseinstaller/setup.exe>.

After installation, you will be asked to review the license agreement. Upon acceptance, you will be prompted for a valid Acumen license key. Upon successful validation, you will be ready to run Acumen.

Offline Installation

If you are unable to connect to the internet, or your firewalls prevent you from completing the online license activation, you can use the Acumen offline installer. The offline installation works like any other application (that is, it doesn't use the Microsoft® ClickOnce technology).



- See *Offline Installer Version* below for steps (skip step 1 if you are installing for the first time).
- If you use the offline installer, you will need to use the offline license activator to activate your license. You can find additional information and steps in the **KB #77921** article.

Updates


Online Installer Version (Automatic Updates)

By default, every time you start Deltek Acumen, it checks for both required and recommended updates. If any are found, a message displays, asking if you would like to install the updates. If you click **Yes**, the updates download and install. After the installation, you will need to close and reopen Acumen in order for the updates to take effect.



You need an Internet connection in order to receive updates.

To enable/disable automatic updates, complete the following steps:

1. Click .
2. At the bottom of the pane, click **Deltek Acumen Options**.

3. On the General tab, deselect **Automatically check for updates when Deltek Acumen starts**.
4. Click **OK**.

Offline Installer Version




If you use the Offline Installer, Acumen will not automatically check for updates. See *Manually Check for Updates* below for manual steps.

To use the offline installer, complete the following steps:

1. Uninstall your current Acumen version.
2. From Internet Explorer, navigate to <https://dsm.deltek.com>.
3. Click **Run Deltek Software Manager**.
4. Log in using your Deltek Customer Care Connect credentials.
5. In the left pane of the Deltek Software Manager, expand the Acumen folder.
6. Expand the Complete folder and select the update you wish to download.
7. Click **Download** at the bottom of the screen.
8. Run the executable (.exe) file. After the update is complete, click **Finish**.

Manually Check for Updates

1. Open Acumen.
2. Click .
3. At the bottom of the pane, click **Deltek Acumen Options**.
4. On the General tab, click **Check for Updates**.

Check to See if an Update is Installed

In Acumen, view the current version number in the bottom right corner of the screen.

Configuring the Fuse.exe.config File

You can tailor the Acumen system configuration file (**Fuse.exe.config**) to meet your specific needs. The file is in an XML format that can be opened with any text editor.



See [Appendix A: Example of a Fuse.exe.config file](#) for an example of the configuration file.

The location of the **Fuse.exe.config** file depends on the type of installation (ClickOnce or Offline).

- Online (ClickOnce) Installation:

```
%USERPROFILE%\AppData\Local\Apps\2.0\Data\O9KY269W.77J\8OG9196B.1OV\fuse
..tion_261286bd7c5fc142_0005.0001_ded710e1a5a06cdc\Data\0.8.5.0
```



The highlighted portion changes based on the installation.

- Offline Installation:

```
program files\deltek\acumen\
```



This is the default location which the user can change at the time of installation.

Useful Configuration File Settings

Online License Activation

To disable online license activation, change the **DisableOnlineLicenseActivation** value to **True**:

```
<setting name="DisableOnlineLicenseActivation" serializeAs="String">
  <value>True</value>
</setting>
```

End User License Agreement

To prevent users from having to agree to the End User Agreement when they first launch Acumen, change the **AreTermsAccepted** value to **True**:

```
<setting name="AreTermsAccepted" serializeAs="String">
  <value>True</value>
</setting>
```

S2 // Benchmarking tab

To hide the S2 // Benchmarking (Acumen Cloud) tab, change the **IsAcumenCloudEnabled** value to **False**:

```
<setting name="IsAcumenCloudEnabled" serializeAs="String">
  <value>False</value>
</setting>
```

Default File Open and Save Location

To set the default File » Open / File » Save location, add the full folder path to the **DefaultFuseFolder** configuration file setting:

```
<setting name="DefaultFuseFolder" = <Full path to folder> serializeAs="String">  
  <value />  
</setting>
```

Installing Acumen in a Citrix® XenApp™ Environment

Installing Acumen on the XenApp Servers

This section covers the steps needed to install Acumen on every XenApp server that will run Acumen.

You can install Acumen in one of two ways:

- Install the application on one server that will run multiple instances of Acumen
- Load balance across multiple servers (highly recommended)



Contact Deltek prior to installation as the licensing scheme differs depending on how you install the application.


Deltek recommends that you enable the CPU Utilization Management in the server farm. Refer to the Citrix documentation for that information.



Acumen does not support streamed applications in XenApp. It only runs in XenApp as an installed application accessed from the server. Therefore, Acumen is installed on the server, and accessed from the server where the processing takes place.

To install Acumen, complete the following steps:

1. Download and extract the latest version of the CD installer from the link provided.
2. Run **setup.exe** and follow the instructions on the screen.
 - On the Select Installation Folder screen:
 - Select the same installation location for all servers.
 - Select **Everyone**.



3. Continue through to the end of the installation.

The next step is to enter the license keys.

Enter the License Keys


After Acumen is installed, run the application on each server at least once in order to enter the license keys.

To enter the license key, complete the following steps on each server:

1. Open Acumen by double-clicking on the desktop icon or accessing it from the Start menu under the Deltek folder.
2. Read and accept the terms of the agreement then click **Continue**.
3. On the Acumen Activation screen, enter the license key provided by Deltek.



Each server will use a different license key.



4. Click **Activate Online**.
5. Close Acumen.


The next step is to publish Acumen in XenApp.

Publish Acumen in XenApp

To publish Acumen in XenApp, complete the following steps:


1. On the Citrix® Delivery Services Console, expand the farm that you will be using.
2. Right-click on **Applications** and select **Publish Application**.

3. On the Name screen, in the **Display name** field, enter **Acumen**.



4. Click **Next**.

5. On the Type screen:
 - a. Select **Application**.
 - b. In the Application Type group box:
 - i. Select **Accessed from a server**.
 - ii. In the **Server application type** field, select **Installed application**.



Acumen does not support the *streamed to server* or *streamed to client* delivery methods in XenApp. It can only run in XenApp as an installed/hosted application accessed from the server, which is the traditional XenApp publishing model.

6. Click **Next**.

- On the Location screen, select the location where Acumen is installed. By default, this is in the program files folder (that is, **C:\Program Files\Acumen\Acumen Fuse\Fuse.exe** or **C:\Program Files (x86)\Acumen\Acumen Fuse\Fuse.exe**)



This location should be the same for all servers.


The screenshot shows the 'Acumen Fuse - Publish Application (4/8)' dialog box. The 'Location' step is selected in the 'Steps' pane on the left. The main area contains the following fields and instructions:

- Location:** Select and configure the resource being published.
- Steps:**
 - Welcome (checked)
 - Basic:**
 - Name (checked)
 - Type (checked)
 - Location (selected)**
 - Servers
 - Users
 - Shortcut presentation
 - Publish immediately
- Enter the application location:** Enter the command line for the application you want to publish. You can also specify a default working directory for users. [More...](#)
- Command line:** "C:\Program Files (x86)\Acumen\Acumen Fuse\Fuse.exe" (with a 'Browse...' button)
- Working directory:** C:\Program Files (x86)\Acumen\Acumen Fuse (with a 'Browse...' button)
- Navigation:** '< Back', 'Next >', and 'Cancel' buttons.

- Click **Next**.

9. On the Servers screen, select the servers that will run Acumen.

If you are load balancing Acumen across multiple servers, which is the recommended approach, then you will have one server per concurrent license.



10. Click **Next**.

- On the Users screen, select only the users that should have access to Acumen in your domain.



The number of users in this list should not exceed the number of users in the license pool.

Acumen Fuse - Publish Application (7/9)

CITRIX

Users
Configure the users who may access the application.

Steps

- ✓ Welcome
- Basic**
- ✓ Name
- ✓ Type
- ✓ Location
- ✓ Streaming
- ✓ Offline access
- ✓ Server access
- ✓ Servers
- ▶ **Users**
- Shortcut presentation
- Publish immediately

Specify the users who can access this application.
To add users, choose a directory type at the bottom and select Add. [More...](#)

Allow anonymous users
 Allow only configured users

Configured users:

- Administrator (CTXS-XA1\Administrator)
- user1 (CTXS-XA1\user1)
- user10 (CTXS-XA1\user10)
- user2 (CTXS-XA1\user2)
- user3 (CTXS-XA1\user3)
- user4 (CTXS-XA1\user4)
- user5 (CTXS-XA1\user5)
- user6 (CTXS-XA1\user6)
- user7 (CTXS-XA1\user7)


Select directory type: Citrix User Selector

Add... Remove

< Back Next > Cancel

- Click **Next**.


13. On the Shortcut presentation screen, select or change options as needed.



14. Click **Next** on each screen until you get to the Limits screen.

15. On the Limits screen:

- Select **Limit instances allowed to run in server farm.**
- In the **Maximum instances** field, select the number of maximum instances equal to the number of concurrent licenses that you have acquired.
- Select **Allow only one instance of application for each user.**




16. Click **Next** until you reach the Appearance screen where you can click **Finish**.

Create a Load Evaluator

If you have more than one concurrent license of Acumen and you are load balancing, you will have to create a load evaluator.


To create a load evaluator, complete the following steps:

1. On the server farm, right-click **Load Evaluators** then select **Add Load Evaluator**.
2. On the Add Load Evaluator dialog box:
 - a. In the **Name** field, enter Acumen Load Balance
 - b. Select **Application User Load Balance**.
 - c. In the **Report full load when the number of users for this application equals** field, enter **1**.
 - d. In the Application field, click **Browse** and select **Acumen Fuse**.



3. Click **OK**.
4. Under Application, right-click on **Acumen Fuse** and select **Other Tasks » Attach application to load evaluator**.

5. On the Assign Load Evaluator dialog box, in the **Load Evaluator** field, select the **Acumen Fuse Load Balance** evaluator that you just created.




6. Click **OK** to finish.


Testing the Deployment

To test the Acumen deployment, complete the following steps:

1. On one of the client computers, use one of the Citrix® Plug-Ins to log into the server farm and run the application.




If you use the full online plug-in and you configured Acumen to display a shortcut in the desktop or start menu, the client should be able to see it now.



Instruct users to allow access to local resources if they are prompted by the Citrix® plug-in while using Acumen.

2. After the application is running, navigate to the Application Menu and click **Open** to see if you have access to the local folders.



Your clients should now be able to run Acumen.

Troubleshooting

Multi-monitor client issues (XenApp Server 4.5 or 5.0)

Please follow the following KB article if you are experiencing issues with multi-monitor configurations: <http://support.citrix.com/article/CTX115637>.

Screen flickering issues (Windows 2003 Server)

Please follow the following KB article if you are experiencing screen flickering and your farm server is Windows 2003-based: <http://support.microsoft.com/kb/955692/en-us>.

Appendix A: Example of a Fuse.exe.config File

The following is an example of a **Fuse.exe.config** file:

```
<?xml version="1.0" encoding="utf-8"?>
<configuration>
  <configSections>
    <sectionGroup name="userSettings" type="System.Configuration.UserSettingsGroup, System,
Version=2.0.0.0, Culture=neutral, PublicKeyToken=b77a5c561934e089">
      <section name="Acumen.Fuse.Properties.Settings" type="System.Configuration.ClientSettingsSection,
System, Version=2.0.0.0, Culture=neutral, PublicKeyToken=b77a5c561934e089"
allowExeDefinition="MachineToLocalUser" requirePermission="false" />
    </sectionGroup>
    <sectionGroup name="applicationSettings" type="System.Configuration.ApplicationSettingsGroup,
System, Version=4.0.0.0, Culture=neutral, PublicKeyToken=b77a5c561934e089">
      <section name="Acumen.Fuse.Properties.Settings" type="System.Configuration.ClientSettingsSection,
System, Version=4.0.0.0, Culture=neutral, PublicKeyToken=b77a5c561934e089" requirePermission="false"
/>
    </sectionGroup>
  </configSections>
  <system.net>
    <defaultProxy>
      <proxy usesystemdefault="True" />
    </defaultProxy>
  </system.net>
  <startup>
    <supportedRuntime version="v4.0" sku=".NETFramework,Version=v4.0" />
  </startup>
  <userSettings>
    <Acumen.Fuse.Properties.Settings>
      <setting name="PracDefaultFontSize" serializeAs="String">
        <value>12</value>
      </setting>
      <setting name="OpenPlanUsername" serializeAs="String">
        <value>SYSADMIN</value>
      </setting>
      <setting name="OpenPlanPassword" serializeAs="String">
        <value>PASSWORD</value>
      </setting>
      <setting name="RecoverFile" serializeAs="String">
        <value />
      </setting>
    </Acumen.Fuse.Properties.Settings>
  </userSettings>
</configuration>
```

```

</setting>
<setting name="RecentWorkbooks" serializeAs="String">
  <value />
</setting>
<setting name="ShowTimeInDates" serializeAs="String">
  <value>False</value>
</setting>
<setting name="UseDefaultMetricLibrary" serializeAs="String">
  <value>True</value>
</setting>
<setting name="DefaultMetricLibraryTemplate" serializeAs="String">
  <value />
</setting>
<setting name="FirstTimeRunning" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ScoreLowerLevel" serializeAs="String">
  <value>50</value>
</setting>
<setting name="ScoreUpperLevel" serializeAs="String">
  <value>75</value>
</setting>
<setting name="UseDefaultExecutiveBriefing" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ExecutiveBriefingTemplate" serializeAs="String">
  <value />
</setting>
<setting name="ShowProjectsProject" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ShowProjectsPrimavera" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ShowProjectsRiskAnalysis" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ShowProjectsExcel" serializeAs="String">
  <value>True</value>

```

```

</setting>
<setting name="ShowProjectsOpenPlan" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ShowProjectsUncefact" serializeAs="String">
  <value>True</value>
</setting>
<setting name="AutoMapCodeFields" serializeAs="String">
  <value>True</value>
</setting>
<setting name="AutoMapUserFields" serializeAs="String">
  <value>False</value>
</setting>
<setting name="ProxyUser" serializeAs="String">
  <value />
</setting>
<setting name="ProxyDomain" serializeAs="String">
  <value />
</setting>
<setting name="ProxyPass" serializeAs="String">
  <value />
</setting>
<setting name="ProxyAuthentication" serializeAs="String">
  <value>False</value>
</setting>
<setting name="HideEmptyRibbons" serializeAs="String">
  <value>False</value>
</setting>
<setting name="DefaultSourceId" serializeAs="String">
  <value>0</value>
</setting>
<setting name="UseNativeMsp" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ShowScoreInRibbonView" serializeAs="String">
  <value>True</value>
</setting>
<setting name="SelectedTheme" serializeAs="String">
  <value>0</value>

```

```

</setting>
<setting name="CheckForUpdates" serializeAs="String">
  <value>True</value>
</setting>
<setting name="DefaultFuseFolder" serializeAs="String">
  <value />
</setting>
<setting name="ShowProjectsAsta" serializeAs="String">
  <value>True</value>
</setting>
<setting name="UseOldScoreCalculationMethod" serializeAs="String">
  <value>False</value>
</setting>
<setting name="ReportConfigFileLocation" serializeAs="String">
  <value />
</setting>
<setting name="UseCodeDescription" serializeAs="String">
  <value>True</value>
</setting>
<setting name="P6SdkDataSource" serializeAs="String">
  <value>PMSDK</value>
</setting>
<setting name="P6SdkUsername" serializeAs="String">
  <value>admin</value>
</setting>
<setting name="P6SdkPassword" serializeAs="String">
  <value>Danni420</value>
</setting>
<setting name="UseDefaultScriptLibrary" serializeAs="String">
  <value>True</value>
</setting>
<setting name="DefaultScriptLibraryTemplate" serializeAs="String">
  <value />
</setting>
<setting name="ToolTipDuration" serializeAs="String">
  <value>300000</value>
</setting>
<setting name="UseCurrentDatesForP6Baselines" serializeAs="String">
  <value>True</value>

```

```

</setting>
<setting name="AreTermsAccepted" serializeAs="String">
  <value>False</value>
</setting>
<setting name="AreAcumenCloudTermsAccepted" serializeAs="String">
  <value>False</value>
</setting>
<setting name="Culture" serializeAs="String">
  <value />
</setting>
<setting name="AvailableCultures" serializeAs="String">
  <value>en,es,it,pt,zh-CHS</value>
</setting>
<setting name="AllowEnterpriseFields" serializeAs="String">
  <value>False</value>
</setting>
<setting name="IsAcumenCloudEnabled" serializeAs="String">
  <value>True</value>
</setting>
<setting name="P6WebHostName" serializeAs="String">
  <value />
</setting>
<setting name="P6WebUsername" serializeAs="String">
  <value>admin</value>
</setting>
<setting name="P6WebPassword" serializeAs="String">
  <value>admin</value>
</setting>
<setting name="P6WebPort" serializeAs="String">
  <value>8206</value>
</setting>
<setting name="P6WebUseHTTPS" serializeAs="String">
  <value>False</value>
</setting>
<setting name="ShowProjectsPhoenix" serializeAs="String">
  <value>True</value>
</setting>
<setting name="Language" serializeAs="String">
  <value />

```

```

</setting>
<setting name="ShowReleaseNotesAfterUpdate" serializeAs="String">
  <value>True</value>
</setting>
<setting name="P6WebSettings" serializeAs="String">
  <value />
</setting>
<setting name="IndentXmlApiData" serializeAs="String">
  <value>False</value>
</setting>
<setting name="P6WebTimeout" serializeAs="String">
  <value>300</value>
</setting>
<setting name="LicenseIdentifier" serializeAs="String">
  <value />
</setting>
<setting name="MspAcumenId" serializeAs="String">
  <value>True</value>
</setting>
<setting name="ExportUncefactFolder" serializeAs="String">
  <value />
</setting>
<setting name="KonaRedirectUri" serializeAs="String">
  <value />
</setting>
<setting name="KonaClientId" serializeAs="String">
  <value />
</setting>
<setting name="KonaClientSecret" serializeAs="String">
  <value />
</setting>
<setting name="KonaAccessToken" serializeAs="String">
  <value />
</setting>
<setting name="KonRefreshToken" serializeAs="String">
  <value />
</setting>
<setting name="KonaRefreshToken" serializeAs="String">
  <value />

```

```

</setting>
<setting name="ExportMspXmlFolder" serializeAs="String">
  <value />
</setting>
<setting name="ImportMspExternals" serializeAs="String">
  <value>False</value>
</setting>
<setting name="OpenPlanPassword2" serializeAs="String">
  <value />
</setting>
<setting name="KonaWebUrl" serializeAs="String">
  <value>https://www.kona.com</value>
</setting>
<setting name="KonaApiUrl" serializeAs="String">
  <value>https://io.kona.com</value>
</setting>
</Acumen.Fuse.Properties.Settings>
</userSettings>
<system.serviceModel>
  <bindings>
    <wsHttpBinding>
      <binding name="WSHttpBinding_IBenchmarkingService" maxBufferPoolSize="1048576"
maxReceivedMessageSize="4194304">
        <security mode="Transport">
          <transport clientCredentialType="None" />
        </security>
      </binding>
    </wsHttpBinding>
  </bindings>
  <client>
    <endpoint address="https://cloudservice.projectacumen.com/BenchmarkingService.svc"
binding="wsHttpBinding" bindingConfiguration="WSHttpBinding_IBenchmarkingService"
contract="Benchmarking.WebService.IBenchmarkingService"
name="WSHttpBinding_IBenchmarkingService" />
  </client>
</system.serviceModel>
<runtime>
  <assemblyBinding xmlns="urn:schemas-microsoft-com:asm.v1">
    <dependentAssembly>
      <assemblyIdentity name="System.IO" publicKeyToken="b03f5f7f11d50a3a" culture="neutral" />
    </dependentAssembly>
  </assemblyBinding>
</runtime>

```




```

    <bindingRedirect oldVersion="0.0.0.0-2.6.6.0" newVersion="2.6.6.0" />
  </dependentAssembly>
  <dependentAssembly>
    <assemblyIdentity name="System.Net.Http" publicKeyToken="b03f5f7f11d50a3a" culture="neutral" />
    <bindingRedirect oldVersion="0.0.0.0-2.2.18.0" newVersion="2.2.18.0" />
  </dependentAssembly>
  <dependentAssembly>
    <assemblyIdentity name="System.Runtime" publicKeyToken="b03f5f7f11d50a3a" culture="neutral" />
    <bindingRedirect oldVersion="0.0.0.0-2.6.6.0" newVersion="2.6.6.0" />
  </dependentAssembly>
  <dependentAssembly>
    <assemblyIdentity name="System.Threading.Tasks" publicKeyToken="b03f5f7f11d50a3a"
culture="neutral" />
    <bindingRedirect oldVersion="0.0.0.0-2.6.6.0" newVersion="2.6.6.0" />
  </dependentAssembly>
  <dependentAssembly>
    <assemblyIdentity name="Microsoft.Office.Interop.MSProject" publicKeyToken="71E9BCE111E9429C"
culture="neutral" />
    <bindingRedirect oldVersion="0.0.0.0-14.0.0.0" newVersion="14.0.0.0" />
  </dependentAssembly>
  <dependentAssembly>
    <assemblyIdentity name="LomaCons.InstallKey.ClientSide" publicKeyToken="DAD7C27F67796724"
culture="neutral" />
    <bindingRedirect oldVersion="0.0.0.0-4.1.414.1502" newVersion="4.1.414.1502" />
  </dependentAssembly>
  <dependentAssembly>
    <assemblyIdentity name="LomaCons.InstallKey.Common" publicKeyToken="DAD7C27F67796724"
culture="neutral" />
    <bindingRedirect oldVersion="0.0.0.0-4.1.414.1502" newVersion="4.1.414.1502" />
  </dependentAssembly>
  <dependentAssembly>
    <assemblyIdentity name="System.Net.Http" publicKeyToken="b03f5f7f11d50a3a" culture="neutral" />
    <bindingRedirect oldVersion="0.0.0.0-4.0.0.0" newVersion="2.2.18.0" />
  </dependentAssembly>
</assemblyBinding>
</runtime>
<applicationSettings>
  <Acumen.Fuse.Properties.Settings>
    <setting name="LicenseKey" serializeAs="String">
      <value />
    </setting>
  </Acumen.Fuse.Properties.Settings>
</applicationSettings>

```

```
</setting>
<setting name="LicenseStorageLocation" serializeAs="String">
  <value />
</setting>
<setting name="DisplayModulesInVersion" serializeAs="String">
  <value>False</value>
</setting>
<setting name="DisableOnlineLicenseActivation" serializeAs="String">
  <value>False</value>
</setting>

</Acumen.Fuse.Properties.Settings>
</applicationSettings>
</configuration>
```



Deltek is the leading global provider of enterprise software and information solutions for professional services firms, government contractors, and government agencies. For decades, we have delivered actionable insight that empowers our customers to unlock their business potential. Over 14,000 organizations and 1.8 million users in approximately 80 countries around the world rely on Deltek to research and identify opportunities, win new business, optimize resource, streamline operations, and deliver more profitable projects. Deltek – Know more. Do more.®

deltek.com